NGU Rapport 92.304

IMPRINT
A Print-Driver Program



Postboks 3006 - Lade 7002 TRONDHEIM Tlf. (07) 90 40 11 Telefax (07) 92 16 20

# **RAPPORT**

Rapport nr. 92.304 ISSN 0800-34			6 Gradering: Åpen				
Tittel: IMPRINT: A PRINT-DRIVER PROGRAM							
Forfatter: Trond H. Torsvik			Oppdragsgiver: NGU				
Fylke:	5		Kommune:				
Kartbladnavn (M=1:250.000)			Kartbladnr. og -navn (M=1:50.000)				
Forekomstens navn og koordinater:			Sidetall: 14 Pris: kr 34,-				
			Karth		-		
Feltarbeid utført:	Rapporto	lato:	Prosj	ektnr.:		Ansvarlig: Teer 5. Keeuring	
	24.11	.92	61	2565.00		Lens Kouning	
Sammendrag:  IMPRINT is a print-dri Almost any graphical of Graphics Kernel Syster	output de	vice can be us	ed du	e to the im	es gene plemer	erated with the IMP system.  Intation of the HALO	
Emneord:		Brukerdokı	ıment	asjon			
Geofysikk		· · · · · ·					
						·	

C	ONTENT	PAGE
1.	INTRODUCTION & SYSTEM REQUIREMENTS	3
2.	IMPRINT FILE TYPES	4
3.	INSTALLATION OF IMPRINT	5
_		-
4.	DESCRIPTION OF IMPRINT	6
	4.1 READ PLOT FILE	8
	4.2 PRINT PLOT FILE	10
	4.3 SELECT PRINTER	10
	4.4 CONFIG PRINTER	11
	4.5 SELECT MONITOR	13
	4.6 MULTIPLE PLOTS	13
	4.7 SET DIRECTORY	14
	4.8 QUIT	14

## 1. INTRODUCTION & SYSTEM REQUIREMENTS

IMPRINT is a print-driver program which handles plot-files generated from the IMP (Interactive Modelling of Potential field data) or GMAP/IAPD systems. Almost any graphical output device can be used due to the implementation of the HALO Graphics Kernel System (Copyright 1983-1992 Media Cybernetics, Inc. All rights reserved).

## System requirement:

- IBM AT or compatible (80286/386/486) computer
- Mathematical co-processor (80287/387/487)
- EGA (colour) or VGA (colour) graphics card
- Hard-disk

## Graphical Output Devices:

- Almost any output device (HALO Drivers)

\*HALO is a registered trademark of Media Cybernetics, Inc.

# 2. IMPRINT FILE TYPES

IMPRINT.BAT - Main 'program'

IMPPRINT.EXE - Plotting program

IMPPRINT.SYS - System file

HALORTB.EXE - HALO driver program

\*.INT/BLU/RED/GRN - Plot file names

HALOIBME.DEV - HALO EGA device driver

HALOIBMV.DEV - HALO VGA device driver

HALO\*\*\*\*.PRN - HALO printer driver

# 3. INSTALLATION OF IMPRINT

- Create a sub-directory named IMPLOT on the hard-disk (drive c) by typing:

## C:>md IMPLOT

- Copy all programs and data-files from the supplied IMPRINT disk to the hard-disk by typing:

- Add IMPLOT directory in the AUTOEXEC.BAT file by typing PATH C:\IMPLOT

# IMPORTANT NOTICE:

Always create a sub-directory IMPLOT and copy all programs/files to this directory.

#### 4. DESCRIPTION OF IMPRINT

Type IMPRINT at the system prompt. This is a batch-file program which loads the HALO driver system (HALORTB.EXE loaded as memory resident) and the main printer program (IMPPRINT.EXE) is then executed. The latter program immediately searches for a system file named IMPPRINT.SYS. This file contains information on the default screen device driver (4.5) and the print device driver and its configuration (4.3 & 4.4).

After start-up the main menu is displayed (Fig. 1). An option in the menu may be selected through the use of the arrow keys, and executed by pressing <ENTER>.

FIGURE 1 Main menu IMPRINT

	IMPPR	INT V. 1.0	(c) 1992	Software by	т.н. т	orsvik & NGU	
٠							
1	DEAD	DI OT-ETI E	Main Men SELECT PRINTER		er-r	DIRECTORY	

MULTIPLE PLOTS

QUIT

PRINTER DRIVER: HALOLJTP.PRN PRINTER PORT : LPT 1

SCREEN DRIVER: HALOIBMV.DEV (VGA) PLOT DIRECTORY:

CONFIG PRINTER

PLOT FILE : NoFile

PRINT PLOT FILE

The main menu has the following options:

OPTION	EFFECT
READ PLOT-FILE PRINT PLOT-FILE SELECT PRINTER CONFIG PRINTER SELECT MONITOR MULTIPLE PLOTS SET DIRECTORY QUIT	LOAD/DISPLAY A PLOT-FILE PRINTS PLOT FILE TO OUTPUT DEVICE SELECT DEFAULT OUTPUT DEVICE CONFIGURE OUTPUT DEVICE SWITCHES BETWEEN VGA OR EGA SUPPORT SELECT SEVERAL PLOT-FILES FOR OUTPUT SELECT PLOT-FILE DIRECTORY QUIT/EXIT TO DOS/UNLOAD HALO DRIVER

Below the main menu the following information is displayed:

- Current printer driver Current screen driver Name of Plot File or the message 'MULTIPLE PLOTS' and number of plots to print
- Printer port
- Name of plot-file Directory

Upon entering this option the current plot-directory (selected via option 'SET DIRECTORY'; 4.7) is sorted and data-files (file-extensions \*.INT) are displayed (Fig. 2). Use cursor arrows to select the appropriate profile file followed by <ENTER>. <u>Use <ESC></u> to leave this option without selecting a file.

After selecting a PLOT-FILE the plot-file is automatically displayed on the screen. Hit any key to return to the main menu. The PLOT-FILE can later be plotted using option 'PRINT PLOT FILE' (4.2).

FIGURE 2 Sorted list of plot-files using option 'READ PLOT FILES'

IMP.INT VMAGER7.INT	LOFOTEN. I	NT MAGER.I	NT PR	770.INT	SNORGE.I	1 =
C:\MAGMOD\*.]	INT (7 fi	les)				THT91
<esc> Quit <en< td=""><td></td><td></td><td><c> Copy</c></td><td><v> View</v></td><td><arrows></arrows></td><td></td></en<></esc>			<c> Copy</c>	<v> View</v>	<arrows></arrows>	

#### 4.2 PRINT PLOT FILE

This option reads plot-files selected under option 'READ PLOT FILE' (4.1) or 'MULTIPLE PLOTS' (4.6) and subsequently prints them to the selected output device, set under option 'SELECT PRINTER' (4.3).

#### 4.3 SELECT PRINTER

With this option a sorted list of output device-drivers with file-extension \*.PRN (on directory \IMPLOT) are displayed. Use cursor arrows to select the appropriate device driver (Cf. HALO manual) followed by <ENTER>. Use <ESC> to leave this option without selecting a file.

This option permits the adjustment of parameters which control the printer output. Use cursor arrows (Up & Down) to locate the appropriate parameter to be changed or <u>QUIT/EXIT option by pressing</u> <<u>ESC></u>. The configuration file IMPPRINT.SYS contains names of the variables which are adjusted using 'CONFIG PRINTER'. Whenever a parameter is changed, the file IMPPRINT.SYS is updated, thus recording the adjustment even after IMPRINT is terminated.

The configuration parameters or <u>Printer Attribute Table</u> varies dependent on the currently defined device drivers (Cf. HALO printer support manual), and a total of 17 attributes (PATTR) can be set (0-16). An example of PATTR setting is shown in Figure 3 (printer driver HALOLJTP.PRN which can be used for the HP DESKJET). Note that the maximum number of output width dots (PATTR 0), dependent on dots pr. inc (PATTR 7) and the maximum number of output height dots (PATTR 1; if supported) is indicated in the right text box. Attributes not supported are always marked with -1 and also written as 'NO SUP' in the right text box.

# FIGURE 3 Example of option 'CONFIG PRINTER'

```
PATTR 0 Output width in dots (-1 normal) : 1200
                                                                                         שו
                                                                                             2400
                                                                                             3148
           Output heigth in dots (-1 normal)
                                                                 : 750
           Image orientation (0 normal 1 landscape): 0
Black/White reversal (0 reversal 1 norm): 0
           Dither Flag (0 dithering 1 no dithering): 0 Form Feed Flag (0 formfeed 1 no form feed: 0
           BIS/DOS flag (0 use BIOS 1 use DOS)
Dots pr inch (0,1,2,3)
                                                                                            0 - 3
                                                                 : 0
        8 Number of copies (0 no copy)
       9 Centering (0 centering 1 no centering)
10 X offset in dots (0 no offset)
                                                                 : 0
                                                                : 0
        11 Y offset in dots (0 no offset)
                                                                 : 0
                                                                 :-1
:-1
        12 Printer ID
                                                                                            NO SUP
                                                                                           NO SUP
        13 COM port
        14 Process ID for EMS
                                                                 :-1
                                                                                            NO SUP
        15 Bold printing
                                                                 :-1
                                                                                            NO SUP
        16 Parallel port (0 LPT1, 1 LPT2, 2 LPT3)
                                                                 :0
```

#### 4.5 SELECT MONITOR

Switches between the VGA and EGA graphic device driver.

#### 4.6 MULTIPLE PLOTS

This option is used to select several plot-files for automatic printing. Upon entering this option the current plot-directory (selected via option 'SET DIRECTORY'; 4.7) is sorted and data-files (file-extensions \*.INT) are displayed (Fig. 2).

- (1) Use cursor arrows to select the appropriate profile file followed by <ENTER>.
- (2) Repeat point 1 until you have 'tagged' all the plot-files you wish to print
- (3) Press <ESC> to end selection of files

After selecting PLOT-FILES, these files can be printed using option 'PRINT PLOT-FILE' (4.2).

# 4.7 SET DIRECTORY

This option sets the current directory for <u>plot files</u> (used in options 4.1, 4.2 & 4.6). Screen & printer device drivers and system software should always be located to directory \IMPLOT (see 3). Directory example : c:\magmod

## 4.8 QUIT

This option updates the IMPPRINT.SYS file (if changed), unload the memory resident HALO88 driver and stops the program (Exit to DOS).